

PERMABOND INTERNATIONAL -- PERMABOND 910 SUPER GLUE -- 8040-00-142-9193

=====
Product Identification
=====

Product ID:PERMABOND 910 SUPER GLUE

MSDS Date:03/22/1985

FSC:8040

NIIN:00-142-9193

MSDS Number: BGZYK

=== Responsible Party ===

Company Name:PERMABOND INTERNATIONAL

Address:480 S. DEAN ST.

City:ENGLEWOOD

State:NJ

ZIP:07631

Info Phone Num:(201) 685-5000

Emergency Phone Num:(201) 685-5000

Prep

arer's Name:PHILIP TOSCANO

CAGE:61078

=== Contractor Identification ===

Company Name:PERMABOND INTERNATIONAL,DIV NATIONAL STARCH & CHEM

Address:480 S. DEAN ST.

Box:City:ENGLEWOOD

State:NJ

ZIP:07631

Country:US

Phone:201-685-5000

CAGE:61078

=====
Composition/Information on Ingredients
=====

Ingred Name:METHYL 2-CYANOACRYLATE

CAS:137-05-3

RTECS #:AS7000000

Fraction by Wt: 90%

Other REC Limits:2 PPM

OSHA PEL:2 PPM/4 STEL

ACGIH TLV:2 PPM/4 STEL; 9192

=====
Hazard
=====

s Identification =====

Routes of Entry: Inhalation:YES Skin:YES Ingestion:YES
Reports of Carcinogenicity:NTP:NO IARC:NO OSHA:NO
Health Hazards Acute and Chronic:INGESTION/SKIN/EYES: IMMEDIATE BONDING OF SKIN OR MOUTH MAY RESULT UPON CONTACT. INHALATION: IRRITATING TO MUCOUS MEMBRANES & THE UPPER RESPIRATORY TRACT.
Explanation of Carcinogenicity:NONE
Effects of Overexposure:INGESTION/SKIN/EYES: IMMEDIATE BONDING OF MOUT OR SKIN MAY RESULT UPON CONTACT.

=====
===== First Aid Measures =====

First Aid:SKIN: FLUSH W/PLENTY OF WATER REMOVE CURED ADHESIVE W/HOT SOAPY WATER. DON'T MECHANICALLY REMOVE ADHESIVE. EYES: FLUSH W/PLENTY OF WATER & GET MED ATT. VAPORS ARE LACHRYMATORY. INHALATION: REMOVE TO FRESH AIR-GIVE ARTIFICIAL RESPIRATION/OXYGEN IF NECESSARY & GET MED ATT. INGESTION: GET MEDICAL ATTENTION.

===== Fire Fighting Measures =====

Flash Point Method:SCC
Flash Point :174F
Extinguishing Media:CO2, DRY CHEMICAL, WATER FOG. IF POLYMERIZATION WON'T BE HAZARDOUS.
Fire Fighting Procedures:WEAR SELF-CONTAINED BREATHING APPARATUS & PROTECTIVE CLOTHING TO PREVENT CONTACT W/SKIN & EYES/INHALATION OF VAPORS.
Unusual Fire/Explosion Hazard:CLOTHS USED TO WIPE UP SPILLS MAY CAUSE RAPID POLYMERIZATION THAT COULD RESULT IN AUTO-IGNITION.

===== Accidental Release Measures =====

Spill Release Procedures:WIPE UP W/CLOTH. SOAK W/WATER TO POLYMERIZE ADHESIVE. FLOOD AREA W/WATER. WHEN CURED, REMOVE CURED FILM W/SCRAPER. WEAR NIOSH APPROVED RESPIRATOR FOR ORGANIC VAPORS/SELF-CONTAINED BREATHING APPARATUS, IF NEEDED & PROTECTIVE CLOTHING.

===== Handling and Storage =====

Handling and Storage Precautions:STORE IN COOL & DRY PLACE. KEEP AWAY FROM HEAT/OPEN FLAME. USE W/ADEQUATE VENTILATION. AVOID CONTACT W/SKIN, EYES/CLOTHING.
Other Precautions:KEEP OUT OF REACH OF CH

CHILDREN. READ INSTRUCTIONS
CAREFULLY. DON'T WEAR RUBBER/CLOTH GLOVES.

===== Exposure Controls/Personal Protection =====

Respiratory Protection:WEAR NIOSH APPROVED RESPIRATOR FOR ORGANIC
VAPORS/SELF-CONTAINED BREATHING APPARATUS. UNDER NORMAL USE, NOT
NEEDED.

Ventilation:PROVIDE LOCAL EXHAUST VENTILATION TO CONTROL VAPORS IN WORK
AREA TO KEEP